PyTorch Tutorial

Chapter 1
인지컴퓨팅연구실

Deep Learning Libraries

Why pytorch

- 다른 Frame work에 비해 Pytorch는 어떠한 장점이 있는가?

풍부한 커뮤니티와 지원

최신 연구와의 밀접한 연관

직관적이고 간결한 코드

Hugging Face

PyTorch Lightning



Start pytorch

- Local의 설치 혹은 Colab 환경을 사용하여 pytorch를 사용

START LOCALLY

Select your preferences and run the install command. Stable represents the most currently tested and supported version of PyTorch. This should be suitable for many users. Preview is available if you want the latest, not fully tested and supported, builds that are generated nightly. Please ensure that you have **met the prerequisites below (e.g., numpy)**, depending on your package manager. Anaconda is our recommended package manager since it installs all dependencies. You can also install previous versions of PyTorch. Note that LibTorch is only available for C++.

NOTE: Latest PyTorch requires Python 3.8 or later.

PyTorch Build	Stable (2.4.0)		Preview (Nightly)	
Your OS	Linux	Mac	Windows	
Package	Conda	Pip	LibTorch	Source
Language	Python		C++ / Java	
Compute Platform	CUDA 11.8	CUDA 12.1	CUDA 12.4	~~ROCm 6.1~~ CPU
Run this Command:	pip3 install torch torchvision torchaudio --index-url https://download.pytorch.org/whl/cu118			



Background knowledge

- Tensor





스칼라	벡터	행렬	3차원 텐서	N차원 텐서
	x[1] = 5	x[1,0] = -3	x[0,1,1] = 8	x[1,3,⋯,1] = 7
				N개 인덱스
0차원	1차원	2차원	3차원	N차원

Background knowledge

- Color image

color image is 3rd-order tensor



Image type	Coordinates
2D grayscale image	(row, col)
2D color image (eg. RGB)	(row, col, channel)
3D grayscale image	(plane, row, col)
3D color image	(plane, row, col, channel)

Video type	Coordinates
2D color video	(time, row, col, ch)
3D multichannel video	(time, plane, row, col, ch)

Pytorch Tutorial

- Pytorch API

Module	Description
Torch	pytorch의 기본 모듈
Torch.autograd	pytorch의 자동 미분 기능을 제공
Torch.nn	신경망 구축을 위한 모듈
Torch.multiprocessing	병렬처리
Torch.utils	자주 사용되는 utility를 제공
torchvision	컴퓨터 비전 작업을 수행하기 위한 도구 제공

Pytorch Tutorial

- Docs & Tutorial



https://pytorch.org/docs/stable/index.html



https://pytorch.org/tutorials/



https://tutorials.pytorch.kr

PyTorch Tutorial

Chapter 2
인지컴퓨팅연구실

Pytorch tutorial

- Loss function & optimizer
- Loss fucntion을 Load 하는 방법
  - Torch.nn.CrossEntropyLoss(), torch.nn.MSELoss() 등의 방법으로 loss fucntion을 호출
- Torch에서 Optimizer 호출
  - Torch.optim.SGD(), torch.optim.Adam() 등의 방법으로 torch.optim을 사용하여 optimizer를 호출

Pytorch tutorial

- 학습을 위한 코드

- Model 생성
- Loss Function Load(혹은 구현)
- Optimizer Load
- Epoch만큼 반복하며, backward를 통한 gradient 계산
- 가중치 갱신

```
for epoch in range(num_epochs):
    optimizer.zero_grad()  # 기울기 초기화
    outputs = model(inputs)  # 모델의 출력 계산
    loss = criterion(outputs, targets)  # 손실 계산
    loss.backward()  # 기울기 계산
    optimizer.step()  # 파라미터 업데이트
```

Pytorch tutorial

- Torch.utils

- torch.utils.data를 통해서 data loading과 관련된 util을 제공
  - Dataset : 데이터셋을 정의할때 상속 받는 class (주로 상속을 통한 사용)
  - DataLoader : batch 단위로 load하고 dataset을 섞는 기능 (주로 상속을 통한 사용)
  - TensorDataset : Tensor들로 이루어진 데이터셋 정의에 사용
  - random_split : 데이터셋을 랜덤하게 여러 개로 나눌때 사용

Pytorch tutorial

- Utils libraray의 기능들

tensorboard : train 과정을 시각화 하는데 사용, tensorflow의 시각화 도구이며 pytorch에서도 지원

checkpoint : 메모리 사용량을 줄이기 위해 그래프에서 제거 후 다시 계산

hooks : 순전파 혹은 역전파 시에 출력을 모니터링

Pytorch tutorial

- Dataset load

```
# MNIST dataset
train_dataset = torchvision.datasets.MNIST(root='../../data',
                                           train=True,
                                           transform=transforms.ToTensor(),
                                           download=True)

test_dataset = torchvision.datasets.MNIST(root='../../data',
                                          train=False,
                                          transform=transforms.ToTensor())

# Data loader
train_loader = torch.utils.data.DataLoader(dataset=train_dataset,
                                           batch_size=batch_size,
                                           shuffle=True)

test_loader = torch.utils.data.DataLoader(dataset=test_dataset,
                                          batch_size=batch_size,
                                          shuffle=False)
```

- Model 구성

```
class NeuralNet(nn.Module):
    def __init__(self, input_size, hidden_size, num_classes):
        super(NeuralNet, self).__init__()
        self.fc1 = nn.Linear(input_size, hidden_size)
        self.relu = nn.ReLU()
        self.fc2 = nn.Linear(hidden_size, num_classes)

    def forward(self, x):
        out = self.fc1(x)
        out = self.relu(out)
        out = self.fc2(out)
        return out

model = NeuralNet(input_size, hidden_size, num_classes).to(device)
```

Pytorch tutorial

- Model train

```
total_step = len(train_loader)
for epoch in range(num_epochs):
    for i, (images, labels) in enumerate(train_loader):
        # Move tensors to the configured device
        images = images.reshape(-1, 28*28).to(device)
        labels = labels.to(device)

        # Forward pass
        outputs = model(images)
        loss = criterion(outputs, labels)

        # Backward and optimize
        optimizer.zero_grad()
        loss.backward()
        optimizer.step()

        if (i+1) % 100 == 0:
            print ('Epoch [{}/{}], Step [{}/{}], Loss: {:.4f}'
                   .format(epoch+1, num_epochs, i+1, total_step, loss.item()))
```

- Model test

```
# In test phase, we don't need to compute gradients (for memory efficiency)
with torch.no_grad():
    correct = 0
    total = 0
    for images, labels in test_loader:
        images = images.reshape(-1, 28*28).to(device)
        labels = labels.to(device)
        outputs = model(images)
        _, predicted = torch.max(outputs.data, 1)
        total += labels.size(0)
        correct += (predicted == labels).sum().item()

    print('Accuracy of the network on the 10000 test images: {} %'.format(100 * correct / total))
```

Pytorch Tutorial

- Torch library의 기본 조작
- Tensor 생성
  torch.tensor(), torch.zeros(), torch.ones(), torch.arrange(), torch.rand, torch.randn() 등

```
shape = (2, 3,)
rand_tensor = torch.rand(shape)
ones_tensor = torch.ones(shape)
zeros_tensor = torch.zeros(shape)

print(f"Random Tensor: \n {rand_tensor} \n")
print(f"Ones Tensor: \n {ones_tensor} \n")
print(f"Zeros Tensor: \n {zeros_tensor}")
```

```
Random Tensor:
 tensor([[0.7835, 0.7065, 0.8801],
        [0.8708, 0.7689, 0.0948]])

Ones Tensor:
 tensor([[1., 1., 1.],
        [1., 1., 1.]])

Zeros Tensor:
 tensor([[0., 0., 0.],
        [0., 0., 0.]])
```

- Tensor 조작
  크기 변경 : torch.view()
  결합 : torch.cat(), torch.stack
  분할 : torch.chunk, torch.split

- 수학적 연산
  기본 연산 : torch.add(), torch.sub(), torch.mul(), torch.div()
  행렬 연산 : torch.mm(), torch.mv(), torch.matmul(), torch.eig()
  통계 연산 : torch.mean(), torch.sum(), torch.median(), torch.std()

Pytorch Tutorial

- Torch.autograd

- 미분 가능한 tensor를 지정 : requires_grad=True 옵션으로 활성화

- 역전파 수행 : tensor.backward()를 호출

- 그레디언트 저장 : tensor.grad를 통해 gradient 값에 접근

```
# no_grad()를 사용하여 추론 수행
with torch.no_grad():
    test_inputs = torch.randn(2, 10)  # 테스트 입력 데이터
    test_outputs = model(test_inputs)
    print("Test Outputs:", test_outputs)

    # 예측 결과를 위한 최댓값 인덱스
    _, predicted = torch.max(test_outputs, 1)
    print("Predicted Classes:", predicted)
```

- 블록 내 gradient 계산 금지 설정 : no_grad()를 통해 제한 (with torch.no_grad로 사용)

- 텐서 연산 기록 추적 : troch.grad_fn을 사용하여 기록 조회

Pytorch Tutorial

- Torch.nn
  신경망을 만들기 위한 library

- Convolution, pooling, padding,
  Recurrent, Dropout, Linear
  등의 model의 구성요소에 대한 기능 제공

Pooling layers

`nn.MaxPool1d`	Applies a 1D max pooling over an input signal composed of several input planes.
`nn.MaxPool2d`	Applies a 2D max pooling over an input signal composed of several input planes.
`nn.MaxPool3d`	Applies a 3D max pooling over an input signal composed of several input planes.
`nn.MaxUnpool1d`	Computes a partial inverse of `MaxPool1d`.
`nn.MaxUnpool2d`	Computes a partial inverse of `MaxPool2d`.

torch.nn

These are the basic building blocks for graphs:

torch.nn

- Containers
- Convolution Layers
- Pooling layers
- Padding Layers
- Non-linear Activations (weighted sum, nonlinearity)
- Non-linear Activations (other)
- Normalization Layers
- Recurrent Layers
- Transformer Layers
- Linear Layers
- Dropout Layers
- Sparse Layers
- Distance Functions
- Loss Functions
- Vision Layers
- Shuffle Layers
- DataParallel Layers (multi-GPU, distributed)
- Utilities
- Quantized Functions
- Lazy Modules Initialization

Pytorch

다음과 같이 torch.nn library를 사용하여 model block 구성

```
class BasicBlock(nn.Module):
    expansion = 1

    def __init__(self, in_channels, out_channels, stride=1, downsample=None):
        super(BasicBlock, self).__init__()
        self.conv1 = nn.Conv2d(in_channels, out_channels, kernel_size=3, stride=stride, padding=1, bias=False)
        self.bn1 = nn.BatchNorm2d(out_channels)
        self.relu = nn.ReLU(inplace=True)
        self.conv2 = nn.Conv2d(out_channels, out_channels, kernel_size=3, stride=1, padding=1, bias=False)
        self.bn2 = nn.BatchNorm2d(out_channels)
        self.downsample = downsample

    def forward(self, x):
        identity = x

        if self.downsample is not None:
            identity = self.downsample(x)

        out = self.conv1(x)
        out = self.bn1(out)
        out = self.relu(out)
        out = self.conv2(out)
        out = self.bn2(out)

        out += identity
        out = self.relu(out)

        return out
```